

## Printer Installation Windows 10 S

Windows 10 S does not support driver install executables (.exe) files, if the .exe is run 10 S will display an error message. You can install a Windows WHQL driver on Windows 10 S using the following steps.


1. Unzip the WHQL driver file.

Name ^	Date modified	Type	Size
WIN_64Bit_WHQL_PCL6PS_MX_D43_1709a	12/22/2017 11:31 AM	File folder	
WIN_64Bit_WHQL_PCL6PS_MX_D43_1709a	11/1/2017 12:55 PM	Microsoft Excel 97-...	83 KB
WIN_64Bit_WHQL_PCL6PS_MX_D43_1709a	11/1/2017 3:28 PM	Microsoft Word Doc...	163 KB
WIN_64Bit_WHQL_PCL6PS_MX_D43_1709a.zip	11/1/2017 2:20 PM	Compressed (zippe...	8,092 KB


2. Run the Installer (.exe) file.

Name ^	Date modified	Type	Size
MX_D43_PCL6_PS_1709a_EnglishUS_64bit.exe	11/1/2017 12:56 PM	Application	8,327 KB
Read Me.txt	11/1/2017 1:02 PM	Text Document	1 KB


- When the pop-up displaying the destination location is displayed browse to a location to where you want to save the extracted driver files. Click OK and Next.



- Allow the files to be extracted.




- When the Driver Installation pop-up is displayed select Cancel




- Browse to where the extracted driver files were saved and copy that folder to a Windows 10 S PC where the printer will be installed.


Name	Date modified	Type	Size
MX_D43_PCL6_PS_1709a_EnglishUS_64bit	12/22/2017 12:01 PM	File folder	
MX_D43_PCL6_PS_1709a_EnglishUS_64bit.exe	11/1/2017 12:36 PM	Application	8,527 KB
Read Me.txt	11/1/2017 1:02 PM	Text Document	1 KB




- Open Windows Settings then Devices.




- Choose Printer & Scanners then choose Add a printer or scanner.




9. Then select "The printer that I want isn't listed".




10. Select "Add a printer using a TCP/IP address or hostname" and then choose Next.




11. Enter the IP address for your printer, be sure "Query the printer and automatically select the driver to use" is not checked. Then select Next.




12. Select Have Disk and Browse to where you copied the Extracted Driver files. Once the driver file has been chosen select OK.




13. Choose the driver file for the Printer you are adding and select Next.



14. Enter the printer name and select Next.



15. After the driver installs select Next and Finish.



16. The installed Printer will appear in the Printers & scanners list.

